


TT191002 – OPENweb - Control Panel Installation


1. If you want to operate OPENweb from another PC (e.g. workstation), you can install OPENweb Control Panel on that PC. On your Workstation PC, start a browser (e.g. Chrome) and type the IP address of the OPENweb server with “/tools” at the end, like this




2. If your OPENweb server setup is not using TCP port 80 (e.g. 85), then you need to use “:85/tools”, for example





3. If you cannot see the OPENweb webpage, please check your network settings. Please also refer to TT191001 to setup the firewall on the OPENweb server PC if required
4. Now click on the “Install” button for Control Panel. This will download the OPENweb Control Panel software to your PC, and you can run it after finished




5. The installation will start. Select “English” and click “OK”





6. Follow the instructions, and accept the default settings. Click “Finish” at the end
7. Start OPENweb Control Panel. First, you need to setup the connection to the OPENweb server. Click the  button



8. Type in the OPENweb server PC IP address, and the TCP port for OPENweb connection, and click “OK”



9. If the settings and connections are OK, then you should see the status icon change to . Click “OK” to start the program



10. Now you can operate OPENweb on the workstation PC

