

TT210604 – FUP - Multiple Selections

1. In FUP, you can multiple select items and then change their properties at the same time. For example, in trend configuration change all the interval to 5.

C:\Users\Admin\AppData\Local\DEOS\FUP XL\2\workspace\prj\Testing\DDC101 - External protocol - TIMETREND

File Extras Help

Main tree

- AAA 1
- AAA 3
- AHU

COSMOS

- RA Humid 2
- RA Temp 2
- OA Humid
- OA Temp
- RA CO2
- RA Humid
- RA Temp

Identification	Slot-no.	Label	Time Basis	Interval	Time
RA Humid 2	7	SIMULAT. F: D08	minute	1	—:—
RA Temp 2	6	SIMULAT. F: D07	minute	1	—:—
OA Humid	5	SIMULAT. F: D05	minute	1	—:—
OA Temp	4	SIMULAT. F: D04	minute	1	—:—
RA CO2	3	SIMULAT. F: D03	minute	1	—:—
RA Humid	2	SIMULAT. F: D02	minute	1	—:—
RA Temp	1	SIMULAT. F: D01	minute	1	—:—

2. To select all items, first click on “Interval” of the first item.

Identification	Slot-no.	Label	Time Basis	Interval	Time
RA Humid 2	7	SIMULAT. F: D08	minute	1	—:—
RA Temp 2	6	SIMULAT. F: D07	minute	1	—:—
OA Humid	5	SIMULAT. F: D05	minute	1	—:—
OA Temp	4	SIMULAT. F: D04	minute	1	—:—
RA CO2	3	SIMULAT. F: D03	minute	1	—:—
RA Humid	2	SIMULAT. F: D02	minute	1	—:—
RA Temp	1	SIMULAT. F: D01	minute	1	—:—

3. Hold down the “Shift” key, click on the “Interval” of the last item.

Identification	Slot-no.	Label	Time Basis	Interval	Time
RA Humid 2	7	SIMULAT. F: D08	minute	1	—:—
RA Temp 2	6	SIMULAT. F: D07	minute	1	—:—
OA Humid	5	SIMULAT. F: D05	minute	1	—:—
OA Temp	4	SIMULAT. F: D04	minute	1	—:—
RA CO2	3	SIMULAT. F: D03	minute	1	—:—
RA Humid	2	SIMULAT. F: D02	minute	1	—:—
RA Temp	1	SIMULAT. F: D01	minute	1	—:—

4. Release the “Shift” key and type “5”. The “Interval” of the first item will change to 5.

Identification	Slot-no.	Label	Time Basis	Interval	Time
RA Humid 2	7	SIMULAT. F: D08	minute	5	—:—
RA Temp 2	6	SIMULAT. F: D07	minute	1	—:—
OA Humid	5	SIMULAT. F: D05	minute	1	—:—
OA Temp	4	SIMULAT. F: D04	minute	1	—:—
RA CO2	3	SIMULAT. F: D03	minute	1	—:—
RA Humid	2	SIMULAT. F: D02	minute	1	—:—
RA Temp	1	SIMULAT. F: D01	minute	1	—:—

5. Press “Enter”, and all the “Interval” will change to 5.

Identification	Slot-no.	Label	Time Basis	Interval	Time
RA Humid 2	7	SIMULAT. F: D08	minute	5	—:—
RA Temp 2	6	SIMULAT. F: D07	minute	5	—:—
OA Humid	5	SIMULAT. F: D05	minute	5	—:—
OA Temp	4	SIMULAT. F: D04	minute	5	—:—
RA CO2	3	SIMULAT. F: D03	minute	5	—:—
RA Humid	2	SIMULAT. F: D02	minute	5	—:—
RA Temp	1	SIMULAT. F: D01	minute	5	—:—

6. To select multiple items, you can use the “CTRL” key. Click the “Interval” of the first item you want to change, hold down the “CTRL” key, and then select the other items.

Identification	Slot-no.	Label	Time Basis	Interval	Time
RA Humid 2	7	SIMULAT. F: D08	minute	5	—:—
RA Temp 2	6	SIMULAT. F: D07	minute	5	—:—
OA Humid	5	SIMULAT. F: D05	minute	5	—:—
OA Temp	4	SIMULAT. F: D04	minute	5	—:—
RA CO2	3	SIMULAT. F: D03	minute	5	—:—
RA Humid	2	SIMULAT. F: D02	minute	5	—:—
RA Temp	1	SIMULAT. F: D01	minute	5	—:—

7. Release the “CTRL” key, type “10” and press “Enter” to change the interval of the select items to 10.

Identification	Slot-no.	Label	Time Basis	Interval	Time
RA Humid 2	7	SIMULAT. F: D08	minute	5	—:—
RA Temp 2	6	SIMULAT. F: D07	minute	5	—:—
OA Humid	5	SIMULAT. F: D05	minute	5	—:—
OA Temp	4	SIMULAT. F: D04	minute	5	—:—
RA CO2	3	SIMULAT. F: D03	minute	5	—:—
RA Humid	2	SIMULAT. F: D02	minute	10	—:—
RA Temp	1	SIMULAT. F: D01	minute	5	—:—

8. To change items with drop down menu (e.g. “Time Basis”), click on “Time Basis” of the first items and use “SHIFT” or “CTRL” keys to multiple select.

Identification	Slot-no.	Label	Time Basis	Interval	Time
OA Humid	5	SIMULAT. F: D05	minute	5	—:—
OA Temp	4	SIMULAT. F: D04	minute	10	—:—
RA CO2	3	SIMULAT. F: D03	minute	5	—:—
RA Humid	2	SIMULAT. F: D02	minute	10	—:—
RA Humid 2	7	SIMULAT. F: D08	minute	5	—:—
RA Temp	1	SIMULAT. F: D01	minute	5	—:—
RA Temp 2	6	SIMULAT. F: D07	minute	10	—:—

9. Double click on “Time Basis” of the first item, change it and press “Enter”.

Identification	Slot-no.	Label	Time Basis	Interval	Time
OA Humid	5	SIMULAT. F: D05	minute	5	—:—
OA Temp	4	SIMULAT. F: D04	minute	10	—:—
RA CO2	3	SIMULAT. F: D03	minute	5	—:—
RA Humid	2	SIMULAT. F: D02	minute	10	—:—
RA Humid 2	7	SIMULAT. F: D08	minute	5	—:—
RA Temp	1	SIMULAT. F: D01	minute	5	—:—
RA Temp 2	6	SIMULAT. F: D07	minute	10	—:—

10. Please note that you’ve to click on the field that you want to change when you select the items, for example, click “Time Basis” if you want to change it, otherwise it will not work.

Identification	Slot-no.	Label	Time Basis	Interval	Time
OA Humid	5	SIMULAT. F: D05	minute	5	—:—
OA Temp	4	SIMULAT. F: D04	second	10	—:—
RA CO2	3	SIMULAT. F: D03	second	5	—:—
RA Humid	2	SIMULAT. F: D02	second	10	—:—
RA Humid 2	7	SIMULAT. F: D08	second	5	—:—
RA Temp	1	SIMULAT. F: D01	second	5	—:—
RA Temp 2	6	SIMULAT. F: D07	second	10	—:—

11. This also works in other places, e.g. System integration Modbus, and BACnet Client configuration, etc.