TT180705 - FUP - Setup a New Controller

1. Start FUP. Click "Project", "New", "Project", to create a new project




2. Type in the new project name, select "English" and click OK




3. Click on the project. Click "Controller", "New", "Controller" to create a new controller




4. Type in the new controller name, select the controller type and click OK




5. Select "Yes" if you may need to use international characters, select "NO" if you use TUP




6. Now an empty controller with the basic macros is created. You can then build your programs for this controller. Please refer to the other TTs on how to create the data points, build the control logics and graphic pages. For now, we can continue with this first




7. To change the controller IP, click on the project, right click, click "Network", "IP-Settings"




8. Type the IP address, press Enter, click the "SAVE" button on the top left corner. Close window



9. To compile the controller, click on the controller, right click, click "Compile"




10. Click OK




11. Compile finished without error, you should see the below messages


12. The default IP address of a new controller is 192.168.170.100, and the subnet mask is 255.255.0.0. To upload the program to the new controller, you need to setup your PC IP address accordingly, for example




- 13. To upload the controller, click on the controller, right click, select "Upload"
- 14. Connect your controller to your PC using a network cable. If it is connect successfully, you should see the below screen with the controller information. Tick all the options below until you see the "Load" button is enabled. Click "Load" to load the controller



- 15. The upload may take a long time. It may also upgrade the controller firmware to the latest version and the controller may need to restart a few times during the upgrade
- 16. Wait until you see the following screen, and your controller is now uploaded with the new program, and the IP is changed to 192.168.170.101




- 17. Now we can use a HTML5 browser to view and setup the controller. Chrome is preferred.
- 18. Start Chrome, and type the controller IP address. Click "Password", "Login"




19. Type in the password, and click "Login"




20. For a new controller, we want to clear all the data and set all parameters to default values we set in FUP. Click "System", "Preset", "Select all options" and click OK




21. Click "Start Preset", and wait until it finished




22. Now we need to set the time zone. Login the controller again, click "Timezone", select your city (or other city with the same time zone), and click "Set Time Zone"



23. Click OK, and wait for a while, and reload the page



24. If the time zone is set correctly, the time in the controller should be correct. You can check it by clicking on "General", "Time"



25. Sometimes the controller language is set to German. To check it, click on "System", "Service. You can change the language by using the drop-down menu in the "Language Setup"



26. Now you've finished the setup of the new controller